

```
# autoloader aliases
install sound-slot-0 /sbin/modprobe snd-card-0
install sound-slot-1 /sbin/modprobe snd-card-1
install sound-slot-2 /sbin/modprobe snd-card-2
install sound-slot-3 /sbin/modprobe snd-card-3
install sound-slot-4 /sbin/modprobe snd-card-4
install sound-slot-5 /sbin/modprobe snd-card-5
install sound-slot-6 /sbin/modprobe snd-card-6
install sound-slot-7 /sbin/modprobe snd-card-7

# Let driver know soundcard model is Fujitsu (Remmelt)
options snd-hda-intel model=fujitsu

# Cause optional modules to be loaded above generic modules
install snd /sbin/modprobe --ignore-install snd $CMDLINE_OPTS &&
{ /sbin/modprobe --quiet --use-blacklist snd-ioc32 ; /sbin/
modprobe --quiet --use-blacklist snd-seq ; }
#
# Workaround at bug #499695 (reverted in Ubuntu see LP #319505)
install snd-pcm /sbin/modprobe --ignore-install snd-pcm
$CMDLINE_OPTS && { /sbin/modprobe --quiet --use-blacklist snd-pcm-
oss ; : ; }
install snd-mixer /sbin/modprobe --ignore-install snd-mixer
$CMDLINE_OPTS && { /sbin/modprobe --quiet --use-blacklist snd-
mixer-oss ; : ; }
install snd-seq /sbin/modprobe --ignore-install snd-seq
$CMDLINE_OPTS && { /sbin/modprobe --quiet --use-blacklist snd-seq-
midi ; /sbin/modprobe --quiet --use-blacklist snd-seq-oss ; : ; }
#
install snd-rawmidi /sbin/modprobe --ignore-install snd-rawmidi
$CMDLINE_OPTS && { /sbin/modprobe --quiet --use-blacklist snd-seq-
midi ; : ; }
# Cause optional modules to be loaded above sound card driver
modules
install snd-emul0k1 /sbin/modprobe --ignore-install snd-emul0k1
$CMDLINE_OPTS && { /sbin/modprobe --quiet --use-blacklist snd-
emul0k1-synth ; }
install snd-via82xx /sbin/modprobe --ignore-install snd-via82xx
$CMDLINE_OPTS && { /sbin/modprobe --quiet --use-blacklist snd-
seq ; }

# Load saa7134-alsa instead of saa7134 (which gets dragged in by
it anyway)
install saa7134 /sbin/modprobe --ignore-install saa7134
$CMDLINE_OPTS && { /sbin/modprobe --quiet --use-blacklist saa7134-
alsa ; : ; }
# Prevent abnormal drivers from grabbing index 0
options bt87x index=-2
options cx88_alsa index=-2
options saa7134-alsa index=-2
options snd-atiixp-modem index=-2
options snd-intel8x0m index=-2
options snd-via82xx-modem index=-2
options snd-usb-audio index=-2
options snd-usb-caiaq index=-2
options snd-usb-ua101 index=-2
options snd-usb-us122l index=-2
options snd-usb-usx2y index=-2
# Ubuntu #62691, enable MPU for snd-cmipci
```

```
options snd-cmipci mpu_port=0x330 fm_port=0x388
# Keep snd-pcsp from being loaded as first soundcard
options snd-pcsp index=-2
# Keep snd-usb-audio from being loaded as first soundcard
options snd-usb-audio index=-2
```